



# NETSCAPE V7.1 EMAIL SETUP


1) OPEN NETSCAPE MAIL AND GO TO FILE | NEW AND CLICK ON ACCOUNT.



2) CLICK NEXT TO CREATE A NEW EMAIL ACCOUNT.



3) PUT YOUR FULL NAME OR NAME THE WAY YOU WOULD LIKE IT TO APPEAR IN YOUR EMAIL MESSAGES. YOUR EMAIL ADDRESS IS WRITTEN THIS WAY : "USERNAME@RFNOW.COM". ("USERNAME" IS YOUR USER NAME) FILL IN YOUR E-MAIL ADDRESS IN THE SPACE PROVIDED AND CLICK NEXT.



The screenshot shows a window titled "Account Wizard" with a close button in the top right corner. The window has a blue header bar. Below the header, the title "Identity" is displayed. The main content area contains the following text: "Each account can have its own identity, which is the information that identifies you to others when they receive your messages." followed by "Enter the name you would like to appear in the 'From' field of your outgoing messages (for example, 'John Smith')." Below this is a text input field labeled "Your Name:" containing the text "John Smith". The next section says "Enter your email address. This is the address others will use to send email to you (for example, 'user@example.net')." followed by a text input field labeled "Email Address:" containing the text "johnsmith@rfnw.com". At the bottom of the window, there are three buttons: "< Back", "Next >", and "Cancel".

4) FILL IN THE VALUES AS THEY APPEAR BELOW. CLICK NEXT.



The screenshot shows a window titled "Account Wizard" with a close button in the top right corner. The window has a blue header bar. Below the header, the title "Server Information" is displayed. The main content area contains the following text: "Select the type of incoming server you are using." followed by two radio buttons: "POP" (which is selected) and "IMAP". Below this is the text "Enter the name of your incoming server (for example, 'mail.example.net')." followed by a text input field labeled "Incoming Server:" containing the text "pop.rfnw.com". The next section says "Enter the name of your outgoing server (SMTP) (for example, 'smtp.example.net')." followed by a text input field labeled "Outgoing Server:" containing the text "smtp.rfnw.com". At the bottom of the window, there are three buttons: "< Back", "Next >", and "Cancel".

5) THIS SHOULD BE THE FIRST PART OF YOUR EMAIL ADDRESS. IT SHOULD AUTOMATICALLY HAVE THE CORRECT USERNAME. JUST VERIFY THAT IT IS CORRECT AND CLICK NEXT.




The screenshot shows a dialog box titled "Account Wizard" with a close button in the top right corner. The main heading is "User Name". Below the heading, there is a text prompt: "Enter the user name given to you by your email provider (for example, 'jsmith')." Below this prompt, the label "User Name:" is followed by a text input field containing the text "johnsmith". At the bottom of the dialog box, there are three buttons: "< Back", "Next >", and "Cancel".

6) JUST LEAVE THE ACCOUNT NAME AS THE EMAIL ADDRESS OR CHANGE IT TO SOMETHING LIKE HOME ACCOUNT, WORK ACCOUNT, ETC. CLICK NEXT TO CONTINUE.



The screenshot shows a dialog box titled "Account Wizard" with a close button in the top right corner. The main heading is "Account Name". Below the heading, there is a text prompt: "Enter the name by which you would like to refer to this account (for example, 'Work Account', 'Home Account' or 'News Account')." Below this prompt, the label "Account Name:" is followed by a text input field containing the text "johnsmith@rfnw.com". At the bottom of the dialog box, there are three buttons: "< Back", "Next >", and "Cancel".

7) THAT'S IT! YOU HAVE NOW SUCCESSFULLY SETUP NETSCAPE TO SEND AND RECEIVE EMAILS. CLICK FINISH TO SAVE THIS SETUP INFORMATION AND DOWNLOAD MESSAGES.



8) ENTER YOUR PASSWORD IN THE SPACE PROVIDED. BE SURE THAT IT IS ALL IN LOWER-CASE. ALSO YOU MAY WANT TO CHECK THE REMEMBER PASSWORD BOX SO YOU DON'T HAVE TO ENTER YOUR PASSWORD EVERY TIME YOU CHECK YOUR EMAIL. CLICK THE OK BUTTON AND YOU CAN NOW SEND AND RECEIVE EMAILS.

